

# 【パッチファイル置き換え手順】

2014/7/7発行  
2015/7/30更新

## ■はじめに・・・(本パッチの必要性について)

ND400ver3.x以前を機器登録している状態で、ND400ver4.0xにバージョンアップ後、再読み込みすると、カメラ情報が削除されてしまう問題があります。

これに解決するには、本パッチを対応させる必要があります。

本パッチはASM10 Ver.2.01上でしか動作致しません。

それ以前のバージョンをご使用の場合は、Ver.2.01にバージョンアップした後に本手順を実施いただきますようお願い致します。

## ■手順

1. パッチをダウンロード(PC保存)する。(2015//7/30更新)
2. ダウンロードファイルをASM10がインストールされているPC上で解凍する。
3. 次の3ファイルが格納されていることを確認する。

①asm10set.exe

②setting.dll

③equipments.xml

4. 下記フォルダ(標準設定でASM10がインストールされている場合)を開き、手順3で確認したファイルを置き換える。

・ファイル①②

C:¥Program Files¥Panasonic¥ASM10

※64bit版の場合は、C:¥Program Files(x86)¥Panasonic¥ASM10

・ファイル③

C:¥Program Files¥Panasonic¥ASM10¥apl.xml

※64bit版の場合は、C:¥Program Files(x86)¥Panasonic¥ASM10¥apl.xml

## ■ファイル①② 置換え先 格納フォルダ

The screenshot shows a Windows Explorer window with the address bar set to <code><< SW\_Preload (C:) >> Program Files >> Panasonic >></code>. The left sidebar shows the 'Folders' section with 'Panasonic' selected. The main pane displays a list of folders with the following columns: '名前' (Name), '更新日時' (Last Modified), and '種類' (Type). The folder 'ASM10' is highlighted with a red border.

名前	更新日時	種類
AdminConsole	2012/12/28 13:06	ファイル フォルダ
<b>ASM10</b>	<b>2014/07/04 12:04</b>	<b>ファイル フォルダ</b>
ASM100	2013/05/22 19:45	ファイル フォルダ
DG-ND200	2011/01/20 16:41	ファイル フォルダ
HD300シリーズ設定ツール	2009/01/20 13:40	ファイル フォルダ
MonitoringClient	2013/12/05 21:08	ファイル フォルダ
Ncr4	2014/03/13 16:47	ファイル フォルダ
ND300設定ツール	2009/01/23 16:21	ファイル フォルダ
ND_Viewer	2013/10/23 19:08	ファイル フォルダ

At the bottom of the window, the status bar shows the selected folder 'ASM10' as a 'ファイル フォルダ' (File Folder) with an update time of '更新日時: 2014/07/04 12:04'.

## ■ファイル③ 置換え先 格納フォルダ

